Advanced player settings: Enable in-browser fullscreen

Last Modified on 07/07/2026 9:08 am IDT

This article is designated for administrators.

About


You can enable in-browser fullscreen through the player's Advanced Settings. This configuration is not exposed in the standard Player Studio interface.

Use this setting to keep playback inside the browser on iPhone and iPad instead of switching to the device's native player.

Access the advanced settings

VOD AUDIO REELS

1. Log in to your Rich Media CMS and click the **Studio** tab.




The Player Studio page displays.


2. Click the player you want to edit from the list (or use the search bar in the top right).

> If you haven't created a player yet, check out our article Create a player for guidance.


Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.



The player settings display.




3. Scroll to the bottom of the player settings and click **Advanced Settings.**




The advanced settings editor opens.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.




Configure in-browser fullscreen

1. In the Advanced Settings editor, hover over **playback** and click the **green + icon.**




   The **Key Name** box displays.

2. In the box, enter inBrowserFullscreen and click the **green check mark** or press 'enter'.




   You'll see the new setting listed.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.



3. Hover over the setting and click the **green edit icon**.



4. In the box that opens, type `true`, then click the small green **checkmark**.



   The value displays.



5. Click **Save** at the top right before exiting.

Optional: Disable double-click to enter fullscreen

By default, double-clicking the player enters fullscreen mode.

To disable this:

1. In the Advanced Settings editor, hover over playback and click the **green + icon**.
2. In the **Key Name** box, enter `config.components.fullscreen.disableDoubleClick`
3. Set the value to `true`.
4. Click **Save**.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.

For API reference, see Kaltura's Playkit JS repository on GitHub.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.