

Using the Kaltura V2 Player Mobile Skin

Kaltura V2 Player Mobile Display


The new Kaltura Player v2 Mobile Display is designed to display only the native device's configuration settings and to minimize the plugin configuration icons on your display. The new Kaltura Player V2 mobile skin is available and can be enabled for Kaltura v2.46 players and later. See [How to Enable the Mobile Player Display](#).

When a player loads on any device, the player uses the device's (native) configuration settings exclusively. The native device is triggered to invoke the relevant selections in the menu.

To enable speed selection on the Player Mobile Skin, you will need to add the flashvar "playbackRateSelector.serverSpeedPlayback" and set it to true.



V2 Mobile Player Display



The following player features/plugins are displayed when you pause viewing:

- Scrubber timeline
- Full screen button
- Share if configured

All other player features/plugins are contained in the [Settings Icon](#) and the [Options Menu](#) (in smart containers). The default display for the Settings Icon, Options menu, and the Share icon are in the upper right region of the video display.

Share Icon


Press Share to display and select the social media options available to share your media. A link is displayed to the media's URL to use to embed into other sites.

Settings Icon

The Settings icons relate to the configurable playback settings that include:

- [Quality Settings](#)
- [Playback Speed](#)
- [Closed Captions](#)


All other player features and plugins are nested in the [Options Menu](#).



Quality Settings

Click to select an option from the Quality Settings menu that appears on your device.


For example – iPad Quality Settings:



Playback Speed

Click to select the Playback Speed value from the menu that appears on your device.

For example – iPad Playback Speed:



Closed Captions

Click Closed Captions to select one of the captions' languages from the menu that appears on your device.


Options Menu

Click on the Options to open the following plugins.

- [Info](#)
- [Related](#)
- [Report](#)

Info


Click on Info to obtain information about the video. For example the video's Name, Description and the number of views.



A video player interface with a dark grey background. In the top right corner, there is a white 'X' icon. The main title 'Sample Big Buck Bunny Trailer (HD)' is displayed in large white font. Below the title, there are two icons: a clock icon followed by the text 'Uploaded on Thu Mar 11 2010' and an eye icon followed by '3,740 Views'. The video content area is mostly obscured by a dark overlay, with the word 'Hey' visible in white text on the left side.

Related


Click on Related to display related videos.



A grid of eight video thumbnails. The top-left thumbnail shows a lion in a grassy field with the text 'Booty Crack - source only profile' at the bottom. The top-middle and middle-middle thumbnails show an underwater scene with sharks and people silhouettes. The top-right and middle-right thumbnails feature the 'Kaltura creating together' logo. The bottom-left thumbnail shows a woman's face. The bottom-middle thumbnail has the text 'No mobile video source available' and a clapperboard icon with a question mark. The bottom-right thumbnail shows abstract yellow and green light patterns.

Report

Click on Report to report content as inappropriate or provide administrators with additional moderation information. Use the drop down menu to select your reason for reporting this content as inappropriate or enter other relevant information.

A dark gray modal dialog box with a white 'X' close button in the top right corner. The title 'Report' is in white. Below it is the instruction 'Please describe your concerns about this video.' in white. There is a white-bordered dropdown menu with 'Sexual Content' selected and a white chevron icon on the right. Below the dropdown is a white-bordered text input field with the placeholder text 'Anything else to add?'. In the bottom right corner, there is a bright blue rounded rectangular button with the word 'Submit' in white.

Report

Please describe your concerns about this video.

Sexual Content

Anything else to add?

Submit

How to Enable the Mobile Player Display

The mobile player display is disabled by default and needs to be enabled.

To enable via the KMC

1. Select the Universal Studio tab and select a player from the Players List.
2. In the Basic Display tab, select the option "Enable new mobile skin"
3. Click Save Player Settings.



Basic Display

Basic settings let you set player name, entry and aspect ratio.

Player's ID: 40401621

Player's Name

General Player

Preview entry / playlist

Entries

Playlist

Sample Audio

Player Dimensions

Constrain Aspect Ratio:

Custom

Width: 560 px



Height: 395 px

Update Version Automatically

Enable new mobile skin