

Customize media display in Canvas

Last Modified on 04/05/2026 6:57 pm IDT

 This article is designated for all users.

About

You can customize the design of a media page in your LMS to control how it looks and what information it displays.

Change the player, hide elements, update the background color, or apply custom CSS for a specific media page.



This feature must be enabled by your administrator in the [entrydesign module](#).


Access the display settings

1. Go to your **My Media** page.
2. Click the **pencil icon** next to the desired media.



The edit media page displays.

3. Click on the **Display** tab.



The **Display** settings display.

Use the Display tab to change or modify an entry's display.

Entry player: ▼
Choose a player for this entry

Show elements:

- Sidebar
- Entry properties
- Entry tabs
- Comments
- Header
- Header logo
- Footer

Choose what elements should show on the page with the video

Background color: □
Choose the color of the entry page background

CSS: No file chosen
Upload a CSS file to customize the entry's page.

Different logo: No file chosen
Add a logo image file to show for this entry only. Default logo size is 325px wide X 41px high. Note: The width of the logo image affects the amount of space available for the Header menu.

Customize

1. Use the following options to adjust the media page layout and appearance.



Available options depend on your administrator's configuration.

- **Entry player** - Select a custom player for the page. The choices available are from a predefined set of players supplied by your administrator.
- **Show elements** - Uncheck the UI elements that you want to hide on the entry page.
 - **Sidebar** - The sidebar refers to the bar to the right of the player. Depending on your application's settings, you may or may not have a sidebar, related media, or a playlist chosen by the administrator.
 - **Entry properties** - The properties are right below the player, containing the entry's name, owner, and 3 counter icons for views, comments and likes.
 - **Entry tabs** - Below the properties tab, the entry tab includes the Details, Share, Attachments and the Actions drop down menu.
 - **Comments** - The comment section, if enabled in your video portal.
 - **Header** - The header includes the entire bar on the top of the video portal screen. If you decide to remove it, it will also remove the logo, and all other links.
 - **Header logo** - The main logo at the top left of video portal screen.
 - **Footer** - The video portal footer.
- **Background color** - Choose a background color for the entry page.
- **CSS** - Choose a CSS file to alter only this single page.
Click on the "Upload CSS" button to apply the change. Note that clicking on this button without uploading a file first will have no effect.
- **Different logo** - Choose a new logo that will replace the existing one when viewing this page. Click on the **Upload logo** button to apply the change (clicking on this button without uploading a file first will have no effect).

2. Click **Save entry theme**.

Example

The following shows a sample configuration where all boxes have been unchecked and the background color was changed.


Use the Display tab to change or modify an entry's display.

Entry player:

Choose a player for this entry

- Show elements:
- Header
 - Header logo
 - Sidebar
 - Entry properties
 - Entry tabs
 - Comments
 - Footer


Choose what elements should show on the page with the video

Background color: 

Choose the color for the background

CSS:

Upload a CSS file to the page.



The resulting media is displayed as follows:

