

Enable Kaltura Room embed in Canvas - Admin guide

Last Modified on 03/10/2026 5:55 pm IST

 This article is designated for administrators.

About

Admins can enable the Kaltura Room embed feature in BSE, allowing faculty to embed rooms directly into LMS content.



This feature is supported only with the [Kaltura Room](#). It does not work for legacy meeting rooms.

Enable the feature

In the **Configuration Management console**, make sure the following modules are enabled:

- [Theming](#) with the 'browseandembed' feature to 'Yes':

Share		
Sidemymedia		
Sideplaylists		
Esogroups/sync		
Statepages		
Styling		
Theming		
Thumbnails		
Twitter		
Uploadmedia		
Userreports		
Watchlater		
Modules / category		
Categoryembed		
Categorymembers		
Categorymoderation		
Categorytheme		
Modules / channels		
Channelcategories		
Channelcollections		
channels	<input type="checkbox"/>	Configured from the channelthemingui module
quizcreation	<input type="text" value="Yes"/>	Configured from the quiz module
personalprofile	<input type="text" value="Yes"/>	Configured from the personal profile module
browseandembed	<input type="text" value="Yes"/>	Configured from the Browseandembed module. Can be used only with V3 of the BSE.
kcapture	<input type="text" value="Yes"/>	Configured from the kaltura capture module
createroom	<input type="text" value="Yes"/>	Enables the Theming-based Create Room modal
recorder	<input type="text" value="Yes"/>	Configured from the Recorder module
youtube	<input type="text" value="Yes"/>	Configured from the youtube module

- [MeetingEntry](#) with the 'EmbedInBSE' setting turned on:

Configuration Management

Server Tools

Backup Configuration
Player replacement tool

Global

Application
AddNew

Auth

Categories

Channels

Client

Debug

EmailService

EmailTemplates

Gallery

Header

Icalendar

Languages

Login

MediaCollaboration

Metadata

Moderation

My-media

Navigation

Player

PlaylistPage

Recaptcha

Search

Security

SharedRepositories

Widgets

Meetingentry

Module Info	
Description	This module will enable your site with the ability to create, publish, and search for Kaltura Meetings Rooms in the site. This module depends on the Newrow module.
Note	Our new room experience is now available for early access. You can try out the new room experience and enable it for your users below. Please note the new room experience does not include all features and functionality currently available in the room experience.

enabled	<input type="checkbox"/> Yes	Enable the Meetingentry module.
allowedUsersOrRoles	<input type="text" value="privateOnly Role"/>	Who are the users allowed to create meeting entries.
advanceEntrance	<input type="text" value="0"/>	How long (in seconds) before the event is scheduled to begin, can attendees join the meeting room, if a moderator started the room.
EmbedInBSE	<input type="checkbox"/> Display	For KAF/LMS integration only - allow the Kaltura rooms to be embedded via the BSE flows (requires advanced room templates)

advancedRoomTemplates

Setup the default room template and available room templates that owners can use for personal rooms.

availableRoomTemplates

- Interactive - Everyone's camera is on by default • Up to 25 visible, 100 total participants. Great for workshops, training sessions, and lively group discussions
- Broadcast studio - Broadcast live from a virtual studio room with no production needed. Solo or with multiple



Both old rooms and new rooms may appear in your instance. The **EmbedInBSE** toggle only controls whether the **new room** can be embedded via BSE.



All of the modules listed above must be enabled. If any are disabled, the configuration cannot be saved and an error will appear.

Configure room cards

1. In the **Configuration Management console**, open the [widgets module](#).
2. Set the default display for embedded room cards in the LMS:
 - **ThumbnailOnSessionCard** – Show or hide the room thumbnail image.
 - **SpeakerInfoOnSessionCard** – Show or hide advanced speaker information (displayed on click).

Configuration Management

Server Tools	Widgets		
<ul style="list-style-type: none"> Backup Configuration Player replacement tool 	ThumbnailOnSessionCard	<input type="text" value="Visible"/>	Choose to hide or display the media's thumbnail on the session cards. Session cards are used in Theming based pages, such as the channel page, profile page, and agenda.
<ul style="list-style-type: none"> Global Application AddNew Auth Categories Channels Client Debug EmailService EmailTemplates Gallery 	SpeakerInfoOnSessionCard	<input type="text" value="Hidden"/>	Choose to hide or display the presenters advanced info card on-click in the session cards. Session cards are used in Theming based pages, such as the channel page, profile page, and agenda.
	SessionCardJoinNowIndication	<input type="text" value="15"/>	Enter the number of minutes prior to the session scheduled start time to display the 'Join now' CTA. Leave empty to set it to 15min.
	<input type="button" value="Save"/>		

3. Save your changes.

Example of a room card

June 1 11:30 AM - 12:00 AM EST

Mastering digital marketing strategies: From content creation to lead conversion

Explore the art of lifelong learning and unlock your potential for continuous growth and success. This session dives into practical strategies, proven techniques, and effective habits to develo ... [Read More](#)



Alexander Reed
Brand Manager, Kaltura



Ella Gartner
EVP Product, Kaltura



Marcus Williams
Product manager, Kaltura

+2



Add your logo to the room

When users click 'Join now', the room opens in a dedicated page with a simple header. The header can display your organization's logo, which is configured through the [Header module](#).

1. In the **Configuration Management console**, open the **Header** module.

Configuration Management

Server Tools

- Backup Configuration
- Player replacement tool

Global

- Application
- AddNew
- Auth
- Categories
- Channels
- Client
- Debug
- EmailService
- EmailTemplates
- Gallery
- Header**
- Icalendar
- Languages
- Login
- MediaCollaboration
- Metadata
- Moderation
- My-media
- Navigation
- Player
- PlaylistPage
- Recaptcha
- Search
- Security

Header

headerStyle	<input type="text" value="light"/>	Which background and matching theme should MediaSpace use for the header?
logoImageUri	<input type="text"/>	Specify a URL for an image to use as the site's header logo. Note: If both logoImageUri and logoImageUpload are filled, the logoImageUri value will take priority. The logo on the site header, footer, and login is limited to max-width 140px and max-height 30px. If you are using the registration modules with the fallback to the header module logo, note that the registration page logo is limited to max-width 343px and max-height 48px.
logoImageUpload	<input type="text" value=""/> <input type="button" value="Upload Logo"/> <input type="button" value="Remove"/>	Specify a URL for an image to use as the site's header logo. Note: If both logoImageUri and logoImageUpload are filled, the logoImageUri value will take priority.
logoAltText	<input type="text" value="home"/>	The 'logoAltText' is an alternative text used for 2 use cases: 1. Accessibility-meant to convey the "why" of the image to screen readers. 2. Functional, in case the image file in 'logoImageUri' field or 'logoImageUpload' field are not available for any reason, the text will show.
logoLink	<input type="text" value="home"/>	The options for defining the behavior when a user clicks the logo are: 1. Enter 'false' if you do not want the logo to be clickable; 2. Enter 'home' to display the home page (displayed when MediaSpace opens); 3. Enter a full URL (starting with http://) to open a different page in a new browser window/tab.
enableUploadButton	<input type="text" value="Enable"/>	Enable, Disable or Show only for logged-in users the 'Add New' button in the site's header
stickyNavbar	<input type="text" value="No"/>	Enable the navigation bar to be sticky on the pages, so when users scroll down, it is always visible. Note: Only available for the theming based header.

2. Upload your logo image.
3. Add alt text (for accessibility and fallback).
4. Save your changes.

The logo displays in the header above the room. The logo is not clickable.

