

Enable live playback in the player

Last Modified on 01/18/2026 3:36 pm IST

 This article is designated for administrators.

About


You can enable live streaming and customize pre-broadcast and post-broadcast slates on your player.



VOD

Access the player settings

1. Log in to your [KMC](#) and click the **Studio** tab.




Thumbnail	Name	ID	Type	Created On	Duration	Plays	Status	...
	Rec - Mar 11, 2...	1_2f40rnle		03/11/2025 23:49	00:53	0	Ready	...

The [Player Studio](#) page displays.

2. Click the player you want to edit from the list (or use the search bar in the top

right).

CONTENT STUDIO ANALYTICS SERVICES DASHBOARD + Create

PLAYER STUDIO UNIVERSAL STUDIO V2 TO V7 TRANSITION TOOL

Customized Players (33) Default Players (2)

33 Players Starred + Create player

Name	ID	Last Modified	Creation Date	Plays (Last 30 days)	Domains (Last 30 days)	...
Smart player	56381652	03/11/2025	03/11/2025	0	0	...
new player	53139222	03/11/2025	08/18/2023	0	0	...
Reels test	56351222	03/04/2025	03/04/2025	1	1	...

The [player settings](#) display.



Test 24360622 Save

PLAYBACK OPTIONS

- Auto Play
- Start Playback Muted
- Auto Pause
- Fallback to Muted Autoplay
- Preload
- See more

ACCESSIBILITY & LANGUAGE

- Localization
- Captions default display
- Transcript
- Extended audio description
- Apply user preferences

NAVIGATION & DISCOVERY

- Navigation
- Related
- Summary & chapters

1360 x 765 Demo video

Set the live plugin

1. Scroll down to the **Engagement & Interactivity** section, find **Live** and click the toggle to open the settings.

Live A red arrow points to a blue switch icon, indicating it is turned on.

Display viewer count 

Pre broadcast slate 

Entry 

URL 

Post broadcast slate 

Entry 

URL 

2. Configure the following:

Display viewer count - Choose whether to display the number of viewers that are watching live directly on the player.

Pre broadcast slate - Add an image or video before a live broadcast has started.

- Entry - Insert a video or image entry ID. Entry will be broadcasted in a loop until the live stream starts. (By default, the entry thumbnail image is used as a background image for this slate.)
- URL - Image only. Insert an image URL that will be displayed until the live broadcast begins. A post slate image or video will play after the live broadcast ends. (By default, the entry thumbnail image is used as a background image for this slate.)

Post broadcast slate - Add an image or video after the live broadcast has ended.

- Entry - Insert a video or image entry ID. Entry will be broadcasted in a loop after the live stream ends.
- URL - Image only. Insert an image URL that will be displayed after the live broadcast has ended.

3. Click **Save** at the top right of the settings page.

For the user guide, see [Live](#).