


# Enable playlists and a playlist side panel in the player

Last Modified on 01/18/2026 3:08 pm IST

 This article is designated for administrators.

## About

You can enable playlists and an optional side panel for navigation and auto-continue.



**VOD**


## Access the player settings

1. Log in to your [KMC](#) and click the **Studio** tab.

The [Player Studio](#) page displays.

2. Click the player you want to edit from the list (or use the search bar in the top

right).

CONTENT STUDIO ANALYTICS SERVICES DASHBOARD + Create

PLAYER STUDIO UNIVERSAL STUDIO V2 TO V7 TRANSITION TOOL

Customized Players (33) Default Players (2)

33 Players Starred  + Create player

Name	ID	Last Modified	Creation Date	Plays (Last 30 days)	Domains (Last 30 days)	...
Smart player	56381652	03/11/2025	03/11/2025	0	0	...
new player	53139222	03/11/2025	08/18/2023	0	0	...
Reels test	56351222	03/04/2025	03/04/2025	1	1	...

The [player settings](#) display.



Test 24360622

PLAYBACK OPTIONS

- Auto Play
- Start Playback Muted
- Auto Pause
- Fallback to Muted Autoplay
- Preload
- [See more](#)

ACCESSIBILITY & LANGUAGE

- Localization
- Captions default display
- Transcript
- Extended audio description
- Apply user preferences

NAVIGATION & DISCOVERY

- Navigation
- Related
- Summary & chapters

1360 x 765

Demo video

## Set playlist display

1. Scroll down to the **Navigation & discovery** section, find **Playlist** and click the toggle to open the settings.

Playlist 

Auto-continue 

Loop 

Countdown 

Duration

2. Configure the following:

- **Auto continue** - choose whether to continue to the next item automatically.
- **Loop** - choose whether to play the playlist in a loop. When selected, the playlist will play automatically, even if **Auto continue** is not selected.
- **Countdown** - choose whether to show the countdown.  
In the **Duration** field, type how long the countdown will display.

3. Click **Save** at the top right of the settings page.

## Set the playlist side panel

**VOD**

1. Scroll down to the next setting which is **Playlist side panel** and click the toggle to open the settings.

Playlist side panel 

Position

Right

Left

Top

Bottom

Expand

Alongside

Over

Expand on First Play

2. Configure the following:

- In **Position**, choose the position of the playlist side panel - Right, Left, Top, or Bottom.
- In **Expand**, choose whether to expand the playlist side panel alongside the video or



over the video.

- In **Expand on First Play**, choose whether to expand the playlist side panel on the first play of the video.

3. Click **Save** at the top right of the settings page.

For the user guide, see [Playlist](#).