

# Remove channels from the navigation bar in Content Hubs

Last Modified on 04/18/2026 12:44 pm IDT

 This article is designated for administrators.

## About

This article explains how to remove or hide channels from the top navigation bar in Video Portal. Removing a channel deletes its menu item without deleting the channel itself. Hiding a channel keeps the menu item but shows it only to specific groups.

You manage all navigation settings from the Configuration Management console, inside the [Navigation module](#).

## Remove a channel


1. Go to your Configuration Management console, and click the **Navigation** module.

You can also navigate directly using a

link: [https://{your\\_video\\_portal\\_URL}/admin/config/tab/navigation](https://{your_video_portal_URL}/admin/config/tab/navigation).

Gallery
Header
Languages
Login
Metadata
Moderation
My-media
<b>Navigation</b>
Player
Recaptcha

The module page displays.



Navigation		Search Configu
showNavigation	Yes ▾	Choose if navigation should be displayed
navigationStyle	Horizontal ▾	Vertical means that a hidden vertical menu appears on the left in all resolutions, Horizontal means that a horizontal menu appears in desktop resolution and vertical menu appears in lower resolutions
showNavbarSearch	Yes ▾	Choose if the search box in the header should be displayed.
includeCategories	Yes ▾	Select 'No' if you don't want the categories to display in main navigation and only want PRE and POST items to appear

2. Scroll down and find the channel you want to remove.
3. Click **Delete** to the right of that item.

**post**  
Add items to the end of the main menu, after the categories. MediaSpace displays the items in the order you define here.

1

**name**  Enter the label for the menu item. The label is displayed in the main navigation bar. **DELETE**

**type**  Select a menu item type to use in the navigation bar. Setting will change according to your selection.

**channel**  **Select Channel**

**items**  
Add items that would be displayed in a drop-down menu **+ Add "items"**

**allowedGroups**  
Select groups to show this item to. Users who are not members of any of these groups will not see this link. Leave empty to show the item to all users. **+ Add "allowedGroups"**

4. Scroll to the bottom of the module page and click **Save**.

Removing the menu item doesn't delete the channel or its content - it only removes the navigation link.

## Limit visibility using 'allowed groups'

Use the 'allowed groups' setting when you want a channel to stay in the navigation bar but only be visible to specific users.



For information on groups, check out our article [What are user groups in Kaltura?](#)

1. Find the channel and click **+Add "allowedGroups"**.

**name**  Enter the label for the menu item. The label is displayed in the main navigation bar. **DELETE**

**type**  Select a menu item type to use in the navigation bar. Setting will change according to your selection.

**channel**  **Select Channel**

**items**  
Add items that would be displayed in a drop-down menu **+ Add "items"**

**allowedGroups**  
Select groups to show this item to. Users who are not members of any of these groups will not see this link. Leave empty to show the item to all users. **+ Add "allowedGroups"**


An additional field opens.

2. Click **Select groups**.

**allowedGroups**  
Select groups to show this item to. Users who are not members of any of these groups will not see this link. Leave empty to show the item to all users.

**Group**  **Select Groups** **DELETE**

3. Type in the groups that should see it, then click **Submit**.



The group displays in the **Group** field.



4. Scroll to the bottom of the module page and click **Save**.

Users who are not members of any of the selected groups won't see the channel in their navigation bar.