

Remove channels from the navigation bar in Video Portal

Last Modified on 11/18/2025 11:56 am IST

 This article is designated for administrators.

About

This article explains how to remove or hide channels from the top navigation bar in Video Portal. Removing a channel deletes its menu item without deleting the channel itself. Hiding a channel keeps the menu item but shows it only to specific groups.

You manage all navigation settings from the Configuration Management console, inside the [Navigation module](#).

Remove a channel


1. Go to your Configuration Management console, and click the **Navigation** module.

You can also navigate directly using a

link: https://{{your_video_portal_URL}}/admin/config/tabs/navigation.



The module page displays.



showNavigation	Yes <input type="button" value="▼"/>	Choose if navigation should be displayed
navigationStyle	Horizontal <input type="button" value="▼"/>	Vertical means that a hidden vertical menu appears on the left in all resolutions. Horizontal means that a horizontal menu appears in desktop resolution and vertical menu appears in lower resolutions
showNavbarSearch	Yes <input type="button" value="▼"/>	Choose if the search box in the header should be displayed.
includeCategories	Yes <input type="button" value="▼"/>	Select 'No' if you don't want the categories to display in main navigation and only want PRE and POST items to appear

2. Scroll down and find the channel you want to remove.
3. Click **Delete** to the right of that item.

post

Add items to the end of the main menu, after the categories. MediaSpace displays the items in the order you define here.

1

name	My new channel	Enter the label for the menu item. The label is displayed in the main navigation bar.	DELETE
type	Channel	Select a menu item type to use in the navigation bar. Setting will change according to your selection.	
channel	393555473-My new channel	Select Channel	
items	Add items that would be displayed in a drop-down menu + Add "items"		
allowedGroups	Select groups to show this item to. Users who are not members of any of these groups will not see this link. Leave empty to show the item to all users. + Add "allowedGroups"		

4. Scroll to the bottom of the module page and click **Save**.

Removing the menu item doesn't delete the channel or its content - it only removes the navigation link.

Limit visibility using 'allowed groups'

Use the 'allowed groups' setting when you want a channel to stay in the navigation bar but only be visible to specific users.



For information on groups, check out our article [What are user groups in Kaltura?](#)

1. Find the channel and click **+Add "allowedGroups"**.


name	My channel	Enter the label for the menu item. The label is displayed in the main navigation bar.	DELETE
type	Channel	Select a menu item type to use in the navigation bar. Setting will change according to your selection.	
channel	Select Channel		
items	Add items that would be displayed in a drop-down menu + Add "items"		
allowedGroups	Select groups to show this item to. Users who are not members of any of these groups will not see this link. Leave empty to show the item to all users. + Add "allowedGroups"		

An additional field opens.

2. Click **Select groups**.

allowedGroups	Select groups to show this item to. Users who are not members of any of these groups will not see this link. Leave empty to show the item to all users.		
Group	Select Groups	DELETE	

3. Type in the groups that should see it, then click **Submit**.



The screenshot shows a 'Select Groups' dialog box. It has an input field labeled 'Enter group name' and another labeled 'Enter Group id or name'. A red arrow points to the second input field. At the bottom are 'Cancel' and 'Submit' buttons. This dialog box is overlaid on a larger form with a 'Group' field containing 'My_new_channel_group'.

The group displays in the **Group** field.

Group My_new_channel_group Select Groups

4. Scroll to the bottom of the module page and click **Save**.

Users who are not members of any of the selected groups won't see the channel in their navigation bar.