

Manage playback speed in the player

Last Modified on 02/09/2026 10:09 pm IST

 This article is designated for administrators.


About

Playback speed control lets viewers change how fast a video plays. As an admin, you can control whether playback speed appears in the player controls, in the settings menu, or is disabled completely.

VOD

Access the player settings

1. Log in to your KMC and click the **Studio** tab.




Thumbnail	Name	ID	Type	Created On	Duration	Plays	Status	...
	Rec - Mar 11, 2...	1_2f40rnle		03/11/2025 23:49	00:53	0	Ready	***

The [Player Studio](#) page displays.

2. Click the player you want to edit from the list (or use the search bar in the top right).



If you haven't created a player yet, check out our article [Create a player](#) for guidance.



Customized Players (33) Default Players (2)

33 Players

Starred + Create player

Name	ID	Last Modified	Creation Date	Plays (Last 30 days)	Domains (Last 30 days)	...
Smart player	56381652	03/11/2025	03/11/2025	0	0	...
new player	53139222	03/11/2025	08/18/2023	0	0	...
Reels test	56351222	03/04/2025	03/04/2025	1	1	...

The player settings display.



Test 24360622

PLAYBACK OPTIONS

- Auto Play
- Start Playback Muted
- Auto Pause
- Fallback to Muted Autoplay
- Preload

See more

ACCESSIBILITY & LANGUAGE

- Localization
- Captions default display
- Transcript
- Extended audio description
- Apply user preferences

NAVIGATION & DISCOVERY

- Navigation
- Related
- Summary & chapters

1360 x 765

Demo video



Set playback speed control

1. In the **Playback options** section find **Speed** and click the toggle to enable the setting.

Speed 

Show speed control

View options



Playback speed 



2. Configure the following:

Show speed control – Choose whether playback speed is available to viewers:

- **Checked** – Viewers can change playback speed. Choose where the control appears using the 'View options' setting below.
- **Unchecked** – Playback speed is hidden from both the player controls and the settings menu.

View options – Choose where viewers change playback speed (only applies when 'Show speed control' is checked):

- **Inline** – Shows a full playback speed menu directly in the player control bar.
- **Settings based** – Shows playback speed in the player settings menu (default).

Playback speed – Defines which playback speed options are available to viewers. Supported speeds: **0.5, 1, 1.5, 2** (default is 1x)

3. Click **Save** at the top right of the settings page.

For the user guide, see [Playback speed in player](#).