

Advanced player setting: Enable in-browser fullscreen

Last Modified on 05/06/2026 8:40 pm IDT

 This article is designated for administrators.

About


You can enable in-browser fullscreen through the player's Advanced Settings. This configuration is not exposed in the standard Player Studio interface.

Use this setting to keep playback inside the browser on iPhone and iPad instead of switching to the device's native player.

Access the advanced settings

VOD **AUDIO** **REELS**

1. Log in to your Rich Media CMS and click the **Studio** tab.



The **Player Studio** page displays.

2. Click the player you want to edit from the list (or use the search bar in the top right).



If you haven't created a player yet, check out our article [Create a player](#) for guidance.

CONTENT STUDIO ANALYTICS SERVICES DASHBOARD [+ Create](#)

PLAYER STUDIO UNIVERSAL STUDIO V2 TO V7 TRANSITION TOOL

Customized Players (33) Default Players (2)

33 Players ☆ Starred [+ Create player](#)

Name	ID	Last Modified	Creation Date	Plays (Last 30 days)	Domains (Last 30 days)	
☆ Smart player	56381652	03/11/2025	03/11/2025	0	0	...
☆ new player	53139222	03/11/2025	08/18/2023	0	0	...
☆ Reels test	56351222	03/04/2025	03/04/2025	1	1	...

The player settings display.

< Smart player 56381652 ☆ ... Save

PLAYBACK OPTIONS

Auto Play

Start Playback Muted

Auto Pause

[See more](#)

CAPABILITIES

Captions default display

Share & Embed

Info

Moderation

Transcript

Summary & chapters

Call to action

Floating

[See more](#)

GENERAL

Localization


Default player ratio

Apply user preferences




1488 x 837 Demo video

3. Scroll to the bottom of the player settings and click **Advanced Settings**.



The Advanced Settings editor displays.



Configure in-browser fullscreen

1. In the **Advanced Settings** editor, hover over **playback** and click the **green + icon**.

The value displays.

```
"inBrowserFullscreen" : bool true
```

5. Click **Save** at the top right before exiting.

Optional: Disable double-click to enter fullscreen

By default, double-clicking the player enters fullscreen mode.

To disable this:

1. In the Advanced Settings editor, hover over playback and click the **green + icon**.
2. In the **Key Name** box, enter `config.components.fullscreen.disableDoubleClick`
3. Set the value to `true`.
4. Click **Save**.



For API reference, see [Kaltura's Playkit JS repository on GitHub](#).