Advanced player settings: Set the default player volume

Last Modified on 07/07/2026 9:10 am IDT

This article is designated for administrators.

About


You can set the default player volume through the player's Advanced Settings. This configuration is not exposed in the standard Player Studio interface.

Use this setting to define the player's starting volume when playback begins. For the user guide, see Playback Functionality.

Access the advanced settings

VOD AUDIO REELS

1. Log in to your Rich Media CMS and click the **Studio** tab.




The Player Studio page displays.


2. Click the player you want to edit from the list (or use the search bar in the top right).

> If you haven't created a player yet, check out our article Create a player for guidance.


Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.



The player settings display.




3. Scroll to the bottom of the player settings and click **Advanced Settings.**




The advanced settings editor opens.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.




Set the default volume

1. In the Advanced Settings tab, hover over **playback** then click the **green + icon.**




   The **Key Name** box displays.

2. In the box, enter `Volume`, then click the **green checkmark** or press 'Enter'.




   You'll see the new setting listed.

3. Hover over the setting and click the **green edit icon**.




4. In the box that opens, enter a value between `0` and `1` (for example, `0.5` for 50% volume), then click the **small green checkmark**.




Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.

5. Click **Save** at the top right before exiting.



Volume assigned a value of 0.5

User experience



Player volume showing 0.5

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.