Advanced player settings: Set a custom tag for VR mode

Last Modified on 07/07/2026 9:10 am IDT

This article is designated for administrators.

About


You can set a custom tag for VR mode through the player's Advanced Settings. This configuration is not exposed in the standard Player Studio interface.

Use this setting to control which tagged videos trigger VR mode in the player. By default, any video tagged 360 triggers VR mode. You can define a different tag to prevent accidental activation.

Access the advanced settings

VOD AUDIO REELS

1. Log in to your Rich Media CMS and click the **Studio** tab.




   The Player Studio page displays.


2. Click the player you want to edit from the list (or use the search bar in the top right).

   If you haven't created a player yet, check out our article Create a player for guidance.


Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.



The player settings display.




3. Scroll to the bottom of the player settings and click **Advanced Settings.**




The advanced settings editor opens.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.



Set a custom tag for VR mode

1. In the Advanced Settings tab, hover over **provider** then click the **green+ icon.**




   The **Key Name** box displays.

2. In the box, enter vrTag, then click the **green checkmark** or press 'enter'.




   You'll see the new setting listed.

3. Hover over the setting and click the **green edit icon**.



   A box containing a null value displays.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.



4. Replace `null` with your custom tag (for example, `my__360__tag`). Do not add quotes as the system will add them automatically.



5. Click the **green check mark** to save your changes.

   The result looks like this:



6. Click **Save** at the top right before exiting.

Now the VR button will only appear for videos that specifically have the tag you set, preventing incorrect playback in VR mode.

Make sure all relevant videos in your account are updated with the new tag. Only videos with this tag will trigger VR mode.

For more details on configuring VR playback, see 360 & VR.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.