Record with Express Capture 2.0 in Blackboard

Content updated: 10/24/2026

This article is designated for all users.

About

Express Capture 2.0 lets you record yourself, your screen, or both, directly from your browser, without installing any software.

You can record video, or audio only. When you record yourself and your screen together, each is saved as a separate stream, so the two can be arranged in different player layouts. Express Capture also includes a teleprompter, background effects, and settings for your video and audio.


Before you start

- This feature requires the Recorder module to be enabled, with the `RecorderVersion` field set to **Version 2.0**.
- Use a supported desktop browser. For details, see Express Capture supported browsers and devices.
- Allow your browser to access your camera and microphone when it asks. If you blocked access before, see What to do if you get locked out of Express Capture.


Open Express Capture

1. Go to your **My Media**.
2. Select **Express Capture** from the **+Create** menu.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.




The **Express Capture** page opens, with a preview of your camera and a toolbar at the bottom.



Use the toolbar to set up and start your recording.


Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.



Choose what to record


Use the toolbar to choose your sources:

- **Camera** - Select the arrow next to the **camera** icon to display the menu.
  The menu has two tabs:
  - **Camera** - Select the camera you want to use, or select **Camera off** to record without your camera. A sound wave shows in place of your camera preview.



  - **Background** - Select **None**, **Light blur**, **Strong blur**, or one of the background images. To use your own image, select **Upload**.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.



- **Microphone** - Select the arrow next to the **microphone** icon to display the menu. Select the microphone you want to use, or select **Mute microphone** to record without sound.
- **Screen** - Select the **screen** icon. Your browser asks what you want to share: a browser tab, a window, or your entire screen. Select one, and then select **Share**. The options depend on your browser.

  If you don't see the **screen** icon, contact your administrator to enable it in the Recorder module.


When you record your camera and your screen together, your camera appears in a small window in the lower-left corner.

Use the teleprompter

The teleprompter shows your script on screen, so you can read it while you record.

1. Select the **teleprompter** icon in the toolbar.
   The teleprompter opens over your camera preview, with a box for your script and controls for how it scrolls and looks.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.




2. Type or paste in your script.
3. Adjust how your script scrolls and looks:
   - To change the scrolling speed, select the arrow next to the **Speed** icon, and then select a speed from **0.5x** to **2x**.
   - To change the text size, select the arrow next to the **text size** icon.
   - To change the contrast of your script, select **Contrast**.
4. Select the **play** icon to start scrolling your script.

To start your script again from the beginning, select **Restart**. To move the teleprompter, drag the dots at the top of it.

Your script appears only on your screen. It isn't part of your recording.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.



To close the teleprompter, select the **teleprompter** icon again, or select the **X**.

Adjust your recording settings

To adjust how your recording looks and sounds, select the **three dots** in the toolbar to open the actions menu.



The menu includes the following:

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.

- **Assistance** - Turn on feedback that helps you get ready to record:
  - **Framing assistance** - Shows a frame on your camera preview, with the message *Position yourself in the frame*. The frame appears when you record only your camera, not when you share your screen.
  - **Lighting assistance** - Shows a message in the upper-left corner when your lighting needs adjusting, for example *Too bright*.
  - **Audio level feedback** - Shows a microphone level meter in the upper-left corner, so you can see how loud you are.



- **Mirror preview** - Turn on to flip your camera preview, like a mirror. (Your recording isn't flipped.)
- **Video orientation** - Select **Landscape** or **Portrait**.
- **Video resolution** - Select **4K (3840×2160)**, **2K (2560×1440)**, **Full HD (1920×1080)**, **HD (1280×720)**, or **SD (640×480)**.
- **Video frame rate** - Select **24 fps**, **25 fps**, **30 fps**, **50 fps**, or **60 fps**.
- **Video format and codec** - Select the file format and codec of your video:
  - **WebM - VP9**
  - **WebM - AV1**
  - **WebM - H.264**
  - **MP4 - H.264**
  - **MP4 - H.265**
  - **MP4 - VP9**
  - **MP4 - AV1**

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.

- **Audio settings** - Turn **Auto echo cancellation**, **Auto noise suppression**, and **Automatic gain control** on or off.

To make Express Capture fill your screen, select the **full-screen** icon at the end of the toolbar.


Record

1. Select **Start recording**.
   A countdown starts, with the message *Get ready to record*. To stop before recording starts, select **Cancel**.
2. Record your video.
   A timer next to the **Finish** button (the stop button) shows how long you've been recording. If your administrator set a maximum recording time, the recording stops automatically when it reaches that time.
3. To take a break, select the **pause** button. To continue, select **Resume**.
4. Select the **Finish** button when you're done.

A preview of your recording opens.

Preview and save your recording

The options for your recording are at the top of the screen.




Play your recording to check it, and then choose one of the following:

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.

- **Record again** - Discard this recording and start again.
- **Download a copy** - Download the recording to your computer. If you recorded your camera and your screen, each one downloads as a separate file, and your browser might ask you to allow multiple downloads. Files are named with the date and time you finished recording, for example `rec-20261023-1443.webm`.
- **Use this** - Upload the recording to your **My Media**.

After you select **Use this**, your recording uploads. If you recorded your camera and your screen together, each stream uploads separately.

A form opens in place of the recorder, where you can edit your recording's details.



- **Name** - Your recording gets a default name with the date and time, for example *Screen Recording - 2026-10-24T10:09:31.473Z*. Enter a name that's easier to find later.
- **Description** - Add a description.
- **Tags** - Add tags to help people find your recording.

Select **Save**. Your recording is private until you publish it. To open it, select **Media Page**.

Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.