

Set Room Mode: XL Room Mode

Last Modified on 08/25/2025 7:29 pm IDT

i Legacy notice

This article documents the **legacy KME Room**. For information on the new room, please visit the [new Kaltura Room documentation](#).

Overview

XL room mode is an optional feature providing moderators with the ability to adjust the room to audiences, larger than 300 and up to 700 participants.

Setting Up XL Room Mode

Setting up XL room mode is very simple and can be done from within the room's settings menu. It is essential to trigger the set-up process at least 10 minutes before session start. To set it up, please go through the following steps:

1. As a moderator, enter the room at least 10 minutes before session start.
2. Open the room's settings menu by clicking the gear icon.
3. Go to the "Room Mode" tab.

Room Settings

Device Settings

Access & Security

Room Mode

Default Permissions

Quick Poll Settings

Chat Settings

Browser Focus

Kaltura Meeting version NR2

Set your room configuration.

☐ Standard room (Virtual Classroom) - All participants are allowed to enable their webcams and mics.

☐ Large room (Webinar) - Only moderators are automatically placed on stage.

☐ Prompt Cam/Mic - Prompt participants to activate their Cam and Mic.

☒ Extra large event for -

700

 participants.

1

 presenters located in

Asia-Pacific

Apply

Apply these changes to relaunch the room in Large Event mode for up to 700 participants and 1 presenters located in Asia-Pacific.

☒ Standard Mute - Participants can unmute themselves any time.

☐ Strong Mute - Participants will require your permission to unmute themselves.


☒ Echo Cancellation - Mute participants during media playback.

Close


Copyright © 2025 Kaltura Inc. All Rights Reserved. Designated trademarks and brands are the property of their respective owners. Use of this document constitutes acceptance of the Kaltura Terms of Use and Privacy Policy.

1


4. Click the "Extra large event" radio button.
5. Choose participants number from the dropdown menu, currently supporting 300-700 participants.
6. Set number of presenters. Presenters are the number of concurrent users expected to publish their audio and video streams.
7. Choose the geo-location where majority of the presenters are located in. This will allocate media server closer to presenters physical location.
8. Click "Apply" to trigger room setup process.
9. Confirm the room restart notification. this will trigger a process of launching the required servers required for hosting the XL session.




10. You will see the following message ribbon while server are being set up



11. Once ready, you will be notified, and asked to confirm room relaunch



12. The room will then be restarted, every user in the room will get refreshed and see the following banner



13. Once you enter the "new" room you are all set to host your XL session.
14. Make sure to end the session for all when you are done. next time the room is launched it will return to it's original settings prior to the XL room mode session.

☐ To enable XL room mode on your account please contact your sales representative.
