

## Enable Kaltura Room embed in Blackboard - Admin guide

Last Modified on 09/02/2025 1:23 pm IDT



This article is designated for administrators.

### **About**

Admins can enable the Kaltura Room embed feature in BSE, allowing faculty to embed rooms directly into LMS content.

For the user guide, see Embed Kaltura Rooms in your LMS via BSE.




This feature is supported only with the new Kaltura Room. It does not work for legacy KME rooms.

### **Enable the feature**

In the Configuration Management console, and make sure the following modules are enabled:

• Theming with the 'browseandembed' feature to 'Yes':



MeetingEntry with the 'EmbedInBSE' setting turned on:





Both old rooms and new rooms may appear in your instance. The **EmbedinBSE** toggle only controls whether the **new room** can be embedded via BSE.

#### **Configuration Management** Server Tools Meetingentry Backup Configuration Player replacement tool Global This module will enable your site with the ability to create, publish, and search for Kaltura Meetings Rooms in the site. This module depends on the Newrow module. Application Description AddNew Auth Our new room experience is now available for early access. You can try out the new room experience and enable it for your users below. Please note the new room experience does not include all features and functionality currently available in the room experience. Note Categories Channels Client Debug Enable the Meetingentry module Yes 🕶 EmailService EmailTemplates Gallery privateOnly Role How long (in seconds) before the event is scheduled to begin, can attendees join the meeting room, if a moderator started the Languages Login For KAF/LMS integration only - allow the Kaltura rooms to be embedded via the $\underline{\textbf{BSE}}$ flows (requires advanced room templates) MediaCollaboration Display 🕶 Metadata Moderation advancedRoomTemplates My-media Navigation Plaver PlaylistPage Recaptcha availableRoomTemplates Search Security SharedRepositories Widgets




All of the modules listed above must be enabled. If any are disabled, the configuration cannot be saved and an error will appear.

# Configure room cards

- 1. In the Configuration Management console, open the widgets module.
- 2. Set the default display for embedded room cards in the LMS:
- ThumbnailOnSessionCard Show or hide the room thumbnail image.
- SpeakerInfoOnSessionCard Show or hide advanced speaker information (displayed on click).




#### **Configuration Management**



3. Save your changes.

## Example of a room card




## Add your logo to the room

When users click 'Join now', the room opens in a dedicated page with a simple header. The header can display your organization's logo, which is configured through the Header module.

1. In the Configuration Management console, open the **Header** module.





- 2. Upload your logo image.
- 3. Add alt text (for accessibility and fallback).
- 4. Save your changes.

The logo is displayed in the header above the room. The logo is not clickable.

