

## Enable skip intro and outro in the player

Last Modified on 01/18/2026 1:42 pm IST

 This article is designated for administrators.


### About

You can add skip buttons that let viewers jump past the intro or credits of a video.



### Access the player settings

1. Log in to your KMC and click the **Studio** tab.




The [Player Studio](#) page displays.

2. Click the player you want to edit from the list (or use the search bar in the top right).



If you haven't created a player yet, check out our article [Create a player](#) for guidance.



Customized Players (33) Default Players (2)

33 Players

Name	ID	Last Modified	Creation Date	Plays (Last 30 days)	Domains (Last 30 days)	...
Smart player	56381652	03/11/2025	03/11/2025	0	0	...
new player	53139222	03/11/2025	08/18/2023	0	0	...
Reels test	56351222	03/04/2025	03/04/2025	1	1	...

The [player settings](#) display.



Test 24360622

PLAYBACK OPTIONS

- Auto Play
- Start Playback Muted
- Auto Pause
- Fallback to Muted Autoplay
- Preload
- [See more](#)

ACCESSIBILITY & LANGUAGE

- Localization
- Captions default display
- Transcript
- Extended audio description
- Apply user preferences

NAVIGATION & DISCOVERY

- Navigation
- Related
- Summary & chapters

Demo video

## Set skip intro/credits

**VOD**

1. In the **Playback options** section find **Skip intro/outro** and click the toggle to enable the setting.

Skip intro/outro

Intro duration [?](#)

Outro duration [?](#)

Hide skip control [?](#)

2. Configure the following:

- **Intro duration** - the Intro will start at the beginning of the video and last the duration you set.
- **Outro duration** - the outro will start at the time counting back from the end of the video. For example, if the video is one minute long and you set the Outro duration to 10 seconds, the outro will begin at the 50-second mark in your video.



These default values will be overridden if an entry has an intro and/or outro configured in its metadata.

- **Hide skip control** - type the duration of time (in seconds) before the skip control is automatically hidden from view.

3. Click **Save** at the top right of the settings page.

For the user guide, see [Skip Intro/Outro](#).