

Advanced player setting: Set the default player volume

Last Modified on 05/06/2026 8:40 pm IDT

 This article is designated for administrators.

About


You can set the default player volume through the player's Advanced Settings. This configuration is not exposed in the standard Player Studio interface.

Use this setting to define the player's starting volume when playback begins. For the user guide, see [Playback Functionality](#).

Access the advanced settings

VOD **AUDIO** **REELS**

1. Log in to your [Rich Media CMS](#) and click the **Studio** tab.



The [Player Studio](#) page displays.

2. Click the player you want to edit from the list (or use the search bar in the top right).



If you haven't created a player yet, check out our article [Create a player](#) for guidance.

CONTENT STUDIO ANALYTICS SERVICES DASHBOARD [+ Create](#)

PLAYER STUDIO UNIVERSAL STUDIO V2 TO V7 TRANSITION TOOL

Customized Players (33) Default Players (2)

33 Players ☆ Starred [+ Create player](#)

Name	ID	Last Modified	Creation Date	Plays (Last 30 days)	Domains (Last 30 days)	
☆ Smart player	56381652	03/11/2025	03/11/2025	0	0	...
☆ new player	53139222	03/11/2025	08/18/2023	0	0	...
☆ Reels test	56351222	03/04/2025	03/04/2025	1	1	...

The player settings display.

< Smart player 56381652 ☆ ... Save

PLAYBACK OPTIONS

Auto Play

Start Playback Muted

Auto Pause

[See more](#)

CAPABILITIES

Captions default display

Share & Embed

Info

Moderation

Transcript

Summary & chapters

Call to action

Floating

[See more](#)

GENERAL

Localization


Default player ratio

Apply user preferences




1488 x 837 Demo video

3. Scroll to the bottom of the player settings and click **Advanced Settings**.




The Advanced Settings editor displays.



Set the default volume

1. In the **Advanced Settings** tab, hover over **playback** then click the **green + icon**.



The **Key Name** box displays.

2. In the box, enter `Volume`, then click the **green checkmark** or press 'Enter'.




You'll see the new setting listed.

3. Hover over the setting and click the **green edit icon**.




4. In the box that opens, enter a value between `0` and `1` (for example, `0.5` for 50% volume), then click the **small green checkmark**.



5. Click **Save** at the top right before exiting.



User experience



Player volume showing 0.5